

Direct_Print Function

Description

The Direct_Print function provides a method to print data directly to a printer. This function bypasses the use of print drivers enabling the use of escape codes to be sent directly to the printer.

Syntax

```
RetVal = Direct_Print(MSG, parameter1, parameters2, ....)
```

Parameters

The first parameter (MSG) is the message or function that is sent to the printer, and it is required. The remaining parameters are optional parameters that control the behavior of the message.

Returns

A value of '1' is returned by Direct_Print if the function call is successful. A negative value is returned if an error is encountered.

See also

[START Direct_Print\(\) message](#)

[STOP Direct_Print\(\) message](#)

[PRINT Direct_Print\(\) message](#)

[PAGE Direct_Print\(\) message](#)

[ABORT Direct_Print\(\) message](#)

[PRINTBIN Direct_Print\(\) message](#)

[Direct_Print Error Codes](#)

Remarks

The START message controls the printer device to be used and print job name for each printing session.

The STOP message will end a print job.

The PAGE message is used to create a page break.

The ABORT message is used to abort the current print job.

The PRINT message is used to send plain text or embedded escape codes to control the output of the printer.

The PRINTBIN message is used to print binary data with embedded nulls.

Example

```

Subroutine Direct_Print_Example(startValue)
Declare Function Direct_Print, Unassigned
If Unassigned(startValue) Then startValue = ''
Equ HP_Bold$ To char(27):(s3B'
Equ HP_Norm$ To char(27):(s-5B'
* This case statement contains the various START options
Begin Case
Case startValue = ''
    retval = Direct_Print('START','','','','') ; * print to default printer
Case startValue = 'ToFile'
    retval = Direct_Print('START','','C:\TEMP\DIRECT_PRINT_EXAMPLE.TXT',1) ; * Print To file
Case startValue = 'Different_Printer'
    retval = Direct_Print('START','HP LaserJet 2200 Series PCL 6','','') ; * print to a specific printer
End case
If retval < 1 then Goto ErrorHandler
* Print 30 lines of bold text
For i = 1 To 30
    retval = Direct_Print('PRINT',HP_Bold$:'This first page contains bold text.')
    If retval < 1 then Goto ErrorHandler
Next i
retval = Direct_Print('PAGE') ; * Force page break
If retval < 1 then Goto ErrorHandler
For i = 1 To 30
    retval = Direct_Print('PRINT',HP_Norm$:'This page contains plain text.')
    If retval < 1 then Goto ErrorHandler
Next i
retval = Direct_Print('PAGE') ; * Force page break
If retval < 1 then Goto ErrorHandler
retval = Direct_Print('PRINT','This page contains concatenated text.',0)
If retval < 1 then Goto ErrorHandler
retval = Direct_Print('PRINT','This page contains concatenated text.',1)
If retval < 1 then Goto ErrorHandler
* End the Print Job
retval = Direct_Print('STOP')
ErrorHandler:
If retval < 1 Then
    Swap @fm With @vm In retval
    call Msg(@Window,'ERROR':retval)
    retval = Direct_Print('ABORT')
End
Return

```