# RTI\_BRW\_GenerateReport

## Description

RTI\_BRW\_GenerateReport is a routine that allows banded reports to be generated with a variety of options.

#### Syntax

RTI\_BRW\_GenerateReport(rptFile, rptName, outputName, rptType, overrideListID, rptDetails, bUseGUI, overrideCfg)

### Parameters

The function has the following parameters:

Parameter	Description		
rptFile	The name of an existing report group or a dynamically generated XML report definition string.		
	Note: If the XML report definition string was derived using the READ action of the RTI_BRWSupport function, a Swap \0D0A\ with @FM command needs to be ran against the XML string. This is because RTI_BRW_GenerateReport looks for the presence of @FM delimiters in rptFile to determine if this is an XML report definition string.		
	If the XML report definition string was derived differently, such as a direct read from the SYSREPOSREPORTS record, then a different step might be required. Newer versions of the BRW embed the version into attribute 1 and the dynamic dictionary data (or an empty string if there are none) into attribute 2 before the report definition string. These need to be removed from the XML string or the following error will result:		
	Data at the root level is invalid. Line 1, position 1		
rptName	If <i>rptFile</i> contains the name of a report group, then <i>rptName</i> contains the name of a specific report to run (or "*" to run all the reports in the group). You may also specify a semicolon-delimited list of report names if desired.		
	Note: The "*", or wildcard, feature and the semicolon delimited list only work with specific CFG_OIBRW configuration settings. In short, only those settings that create new engines and then close them after each report will work properly. See the CFG_OI BRW Configuration article for more information.		
outputName	The path and name of the file to save the output to (if producing a PDF, HTM, etc. document). Leave this blank to generate printed output.		
rptType	The type of output to generate, and can be PDF, TIFF, HTML, TEXT, XLS, or XLSX (or PRINT to generate printed output, but that isn't really needed if you leave <i>outputName</i> blank).		
overrideListID	The ID of a saved list that contains the record keys you want this report generation to use. If there is no <i>overrideListID</i> specified, but there <i>is</i> an active select list when RTI_BRW_GenerateReport is called, then the active list will be used instead.		
	Note: There is evidence that savelists with a space in the name will create problems. Use savelists without spaces to be save.		

	Attribute	rptType=PDF	<i>rptType=</i> PRINT or "" ( <i>bUseGUI</i> should be 0 or "")	
	<1, 1>	Owner password	Printer name (as known by the Windows Print Manager)	
	<1, 2>	User password	Number of copies	
	<1, 3>	Access permissions - a string with any of the following characters: • <i>C</i> =Copying content allowed • <i>E</i> =Editing content allowed • <i>A</i> =Annotation editing allowed • <i>P</i> =Printing allowed	0 or "" for Portrait, 1 for Landscape	
	<1, 4>	Not applicable	<1, 4, 1> = Left Margin (Hundreds of an inch, i.e., 100=1") <1, 4, 2> = Top Margin (Hundreds of an inch, i.e., 100=1") <1, 4, 3> = Right Margin (Hundreds of an inch, i.e., 100=1") <1, 4, 4> = Bottom Margin (Hundreds of an inch, i.e., 100=1")	
	<1, 5>	Not applicable	Page size code	
	<1, 6>	Not applicable	Print Preview caption. (Only available in Ol v10, otherwise, not applicable.)	
	For all report types (i.e., <i>rptType</i> can be set to anything), <1, 1, 1> can be set to a literal "UID" and <1, 1, 2> can be set to any custom value. Doing this informs the BRW that this report has a unique identifier, which can be used in the INIT or TERM actions of the designated OI_BRW_FILTER hook.			
bUseGUI	Value I	Behavior		
	0 or "" Prints the report silently to the default printer. (If configured for outputting to a file, the file is generated without any prompting.)			
	1 If <i>rptType</i> is set to empty or "PRINT", a value of 1 shows a Print Dialog for the report and then prints to the specified printer. If <i>rptType</i> is set to a supported file type, a value of 1 shows a Configuration Dialog specific to the file type.			
	2 If <i>rptType</i> is set to empty or "PRINT", a value of 2 displays the report in the preview window. If <i>rptType</i> is set to a supported file type, a value of 2, it works the same as when <i>bUseGUI</i> is set to 1.			
	<ul> <li>OECGI Invocation Only - Override configuration settings to be used for this instance of the BRW. While the format of this setting uses the same attributes as the CFG_OIBRW configuration record, no defaults will be applied. Therefore, each attribute will have to be explicitly populated (i.e., <i>fully resolved</i>) with the correct value. See the notes regarding each attribute's default value in the the CFG_OIERW Configuration article to understand how to resolve these values. The purpose for an override setting is to ensure that systems like O4W can call the BRW with applicable configuration settings. For instance, the default configuration might be to share the engine, but O4W systems require a new connection.</li> <li>Note: For OI 9.4 and earlier, even if this is not an OECGI invocation, pass in an empty string to avoid a VNAV error. OI 10 will have a fix for this issue.</li> </ul>			
overrideCfg	RW Configura O4W can call O4W systems Note: For OI	ation article to understand how to resolve these values. The the BRW with applicable configuration settings. For instar s require a new connection. 9.4 and earlier, even if this is not an OECGI invocation	nce, the default configuration might be to share the engine, but	
	RW Configura O4W can call O4W systems Note: For OI	ation article to understand how to resolve these values. The the BRW with applicable configuration settings. For instar s require a new connection. 9.4 and earlier, even if this is not an OECGI invocation	nce, the default configuration might be to share the engine, but	
	RW Configura O4W can call O4W systems Note: For OI have a fix for	ation article to understand how to resolve these values. The the BRW with applicable configuration settings. For instar s require a new connection. 9.4 and earlier, even if this is not an OECGI invocation r this issue.	nce, the default configuration might be to share the engine, but	
	RW Configura O4W can call O4W systems Note: For OI have a fix for Value	ation article to understand how to resolve these values. The the BRW with applicable configuration settings. For instar s require a new connection. 9.4 and earlier, even if this is not an OECGI invocation of this issue.	nce, the default configuration might be to share the engine, but	
	RW Configura         O4W can call         O4W systems         Note: For OI         have a fix for         Value         0	ation article to understand how to resolve these values. The BRW with applicable configuration settings. For instarts require a new connection.         9.4 and earlier, even if this is not an OECGI invocation of this issue.         Meaning         Success	nce, the default configuration might be to share the engine, but	
	RW Configura         O4W can call         O4W systems         Note: For OI         have a fix for         0         -1	ation article to understand how to resolve these values. The BRW with applicable configuration settings. For instarts require a new connection.         9.4 and earlier, even if this is not an OECGI invocation of this issue.         Meaning         Success         Either parameter "reportFile" or "reportName" is null ("")	nce, the default configuration might be to share the engine, but	
Returns	RW Configura         O4W can call         O4W systems         Note: For OI         have a fix for         0         -1         1	ation article to understand how to resolve these values. The BRW with applicable configuration settings. For instanding sequire a new connection.         9.4 and earlier, even if this is not an OECGI invocation of this issue.         Meaning         Success         Either parameter "reportFile" or "reportName" is null ("")         Report definition is null - specified report is not on file	nce, the default configuration might be to share the engine, but	

# Remarks

Multiple reports, even from different report groups, can be ran from a single **RTI\_BRW\_GenerateReport** call through @RM delimited values for each parameter. This is similar to the way Set\_Property supports @RM delimited parameters. While multiple reports can be specified to export to a file, this cannot be used to create a single file that contains all reports. Each report must have its own file name or older reports will be overwritten.

**RTI\_BRW\_GenerateReport** is the only way to create PDF reports without the use of the Presentation Server. Using **RTI\_BRWSupport** or the LOADREPORT **Set\_Printer** message both work through OIPI.Net, which requires the Presentation Server.

Dynamically created XML report definitions do not support Dynamic Dictionaries. These will come through as plain text.

See the notes for the *rptFile* parameter for important information when passing in dynamically generated XML report definition strings.

#### See Also

RTI\_BRWSupport