

Run Report Reference

This chapter contains reference information for keywords, format modifiers and file creation using the Run_Report command.

Property	Description
Run_Report subroutine	Runs Report Builder reports.
AVERAGE	The AVERAGE Run_Report keyword is used to generate the average of a numeric column and display it at the end of the report.
BREAK-ON	Break-On causes Run_Report to put a physical break in the report as the value of a column changes.
By and By-DSND	Sorts data within a Run_Report report.
COLFONT	Use Colfont to set the font for a specific column in a report
COLHDRFONT	Use COLHDRFONT to set the font for the entire header row.
COLHEAD	Use COLHEAD to create an alternate column heading for a column.
COLSHADE	This Run_Report keyword is used to set the percentage of shading on a column within the report.
COLSIZE	Used to determine the width of a column within a Run_Report statement.
COL-HDR-SUPP	COL-HDR-SUPP suppresses the column headings (column titles) that are automatically printed at the top of each page for each column being displayed.
DBL-SPC	The modifier DBL-SPC causes a blank line to be printed between each row on the report.
DET-SUPP	Used with Total and Average, DET-SUPP causes a value to be printed at the bottom of the report, and a subtotal or average to be printed at each control break.
FONT	Use Font to set the default font for the body of the report.
Footing	The Footing keyword will cause Run_Report to produce a running page footing (text at the bottom of each page). The footing can contain text, page numbers, dates, and other information.
FTRFONT	Use FTRFONT to set the font for the report footer.
Grand-Total	Grand-Total changes the text that accompanies the final total generated by the Total keyword within a Run_Report statement..
GRID	GRID will print gridlines between the columns and rows.
Heading	The Heading keyword will cause the Run_Report command to produce a running page heading. The heading can contain text, page numbers, dates, and other information.
HDRFONT	Use Hdrfont to set the font for the report heading.
ID-SUPP	Run_Report will always print the key column in the leftmost column of the report. ID-SUPP causes this column not to be printed.
JustLen	Use the keyword JustLen to override the justification or display length of a column as stored in the dictionary. You can override the justification or display length separately, or can combine the override specification in one command.
LANDSCAPE	LANDSCAPE will print the report in landscape mode.
LEGAL	LEGAL will print the report to legal sized paper dimensions.
Limit	The Limit keyword restricts the output of data from a multi-valued column to those values that meet specified criteria.
LPTR	The use of any of these keywords will send the report directly to the default printer.
(M	Previews the report in a maximized preview window.
MARGINS	Use MARGINS to specify the margin for pages within a report.
NUMCOLUMNS	Use NUMCOLUMNS to repeat the selected columns of data within a report.
OConv	Use the keyword OConv to specify a new or alternate output conversion (output format) for a column.
(P	The use of any of these keywords will send the report directly to the default printer.
PAPERSIZE	Use PAPERSIZE to print reports to a specific papersize.
PORTRAIT	PORTRAIT will print the report in portrait mode.
PRINTER	The use of any of these keywords will send the report directly to the default printer.

SCREEN	SCREEN will send the report to the preview window. By default all Run_Report commands use this setting.
T	The T keyword is used to print the total rows processed at the bottom of the report.
Total	Total is used to generate the sum of a numeric column and display it at the end of a report generated through Run_Report.
USING	The Using keyword causes the Run_Report to use a dictionary other than the dictionary of the table being listed or selected.
Using Format Modifiers in Run_Report Statements	The various format modifier keywords can be inserted anywhere into a Run_Report statement (as long as they are not in the middle of a clause).
File Creation Using Run_Report	The Run_Report facility allows for the creation of various file types, such as PDF, HTML and RTF. This is accomplished through the use of keywords in the Run_Report statement.

Search this documentation

Recently Updated Pages

[Run Report Reference](#)

Dec 03, 2015 • updated by [Corby Nagel](#) • [view change](#)

[OConv](#)

Dec 01, 2015 • updated by [Corby Nagel](#) • [view change](#)

[Footing](#)

Dec 01, 2015 • updated by [Corby Nagel](#) • [view change](#)

[COL-HDR-SUPP](#)

Sept 17, 2015 • updated by [SRP Support](#) • [view change](#)

[DBL-SPC](#)

Sept 17, 2015 • updated by [SRP Support](#) • [view change](#)