

# Run Report Reference

This chapter contains reference information for keywords, format modifiers and file creation using the Run\_Report command.

Property	Description
<a href="#">Run_Report subroutine</a>	Runs Report Builder reports.
<a href="#">AVERAGE</a>	The AVERAGE Run_Report keyword is used to generate the average of a numeric column and display it at the end of the report.
<a href="#">BREAK-ON</a>	Break-On causes Run_Report to put a physical break in the report as the value of a column changes.
<a href="#">By and By-DSND</a>	Sorts data within a Run_Report report.
<a href="#">COLFONT</a>	Use Colfont to set the font for a specific column in a report
<a href="#">COLHDRFONT</a>	Use COLHDRFONT to set the font for the entire header row.
<a href="#">COLHEAD</a>	Use COLHEAD to create an alternate column heading for a column.
<a href="#">COLSHADE</a>	This Run_Report keyword is used to set the percentage of shading on a column within the report.
<a href="#">COLSIZE</a>	Used to determine the width of a column within a Run_Report statement.
<a href="#">COL-HDR-SUPP</a>	COL-HDR-SUPP suppresses the column headings (column titles) that are automatically printed at the top of each page for each column being displayed.
<a href="#">DBL-SPC</a>	The modifier DBL-SPC causes a blank line to be printed between each row on the report.
<a href="#">DET-SUPP</a>	Used with Total and Average, DET-SUPP causes a value to be printed at the bottom of the report, and a subtotal or average to be printed at each control break.
<a href="#">FONT</a>	Use Font to set the default font for the body of the report.
<a href="#">Footing</a>	The Footing keyword will cause Run_Report to produce a running page footing (text at the bottom of each page). The footing can contain text, page numbers, dates, and other information.
<a href="#">FTRFONT</a>	Use FTRFONT to set the font for the report footer.
<a href="#">Grand-Total</a>	Grand-Total changes the text that accompanies the final total generated by the Total keyword within a Run_Report statement..
<a href="#">GRID</a>	GRID will print gridlines between the columns and rows.
<a href="#">Heading</a>	The Heading keyword will cause the Run_Report command to produce a running page heading. The heading can contain text, page numbers, dates, and other information.
<a href="#">HDRFONT</a>	Use Hdrfont to set the font for the report heading.
<a href="#">ID-SUPP</a>	Run_Report will always print the key column in the leftmost column of the report. ID-SUPP causes this column not to be printed.
<a href="#">JustLen</a>	Use the keyword JustLen to override the justification or display length of a column as stored in the dictionary. You can override the justification or display length separately, or can combine the override specification in one command.
<a href="#">LANDSCAPE</a>	LANDSCAPE will print the report in landscape mode.
<a href="#">LEGAL</a>	LEGAL will print the report to legal sized paper dimensions.
<a href="#">Limit</a>	The Limit keyword restricts the output of data from a multi-valued column to those values that meet specified criteria.
<a href="#">LPTR</a>	The use of any of these keywords will send the report directly to the default printer.
<a href="#">(M</a>	Previews the report in a maximized preview window.
<a href="#">MARGINS</a>	Use MARGINS to specify the margin for pages within a report.
<a href="#">NUMCOLUMNS</a>	Use NUMCOLUMNS to repeat the selected columns of data within a report.
<a href="#">OConv</a>	Use the keyword OConv to specify a new or alternate output conversion (output format) for a column.
<a href="#">(P</a>	The use of any of these keywords will send the report directly to the default printer.
<a href="#">PAPERSIZE</a>	Use PAPERSIZE to print reports to a specific papersize.
<a href="#">PORTRAIT</a>	PORTRAIT will print the report in portrait mode.
<a href="#">PRINTER</a>	The use of any of these keywords will send the report directly to the default printer.

<a href="#">SCREEN</a>	SCREEN will send the report to the preview window. By default all Run_Report commands use this setting.
<a href="#">T</a>	The T keyword is used to print the total rows processed at the bottom of the report.
<a href="#">Total</a>	Total is used to generate the sum of a numeric column and display it at the end of a report generated through Run_Report.
<a href="#">USING</a>	The Using keyword causes the Run_Report to use a dictionary other than the dictionary of the table being listed or selected.
<a href="#">Using Format Modifiers in Run_Report Statements</a>	The various format modifier keywords can be inserted anywhere into a Run_Report statement (as long as they are not in the middle of a clause).
<a href="#">File Creation Using Run_Report</a>	The Run_Report facility allows for the creation of various file types, such as PDF, HTML and RTF. This is accomplished through the use of keywords in the Run_Report statement.

---

## Search this documentation

## Recently Updated Pages

### [Run Report Reference](#)

Dec 03, 2015 • updated by [Corby Nagel](#) • [view change](#)

### [OConv](#)

Dec 01, 2015 • updated by [Corby Nagel](#) • [view change](#)

### [Footing](#)

Dec 01, 2015 • updated by [Corby Nagel](#) • [view change](#)

### [COL-HDR-SUPP](#)

Sept 17, 2015 • updated by [SRP Support](#) • [view change](#)

### [DBL-SPC](#)

Sept 17, 2015 • updated by [SRP Support](#) • [view change](#)