

DDEERROR

Applies to

Edit box, edit line.

Description

Returns any error code generated by the DDE connection or activity processes. Use with `Get_Property`, only.

Usage

`errorcode` = `Get_Property` (*objectname*, "DDEERROR")

Remarks

Value returned by `Get_Property`:

Value	Description																																				
<i>errorcode</i>	Returns 0, when no error has occurred.																																				
	<table><tr><th>Code</th><th>Description</th></tr><tr><td>0x4001</td><td>DMLERR_BUSY</td></tr><tr><td>0x4002</td><td>DMLERR_DATAACKTIMEOUT</td></tr><tr><td>0x4003</td><td>DMLERR_DLL_NOT_INITIALIZED</td></tr><tr><td>0x4004</td><td>DMLERR_DLL_USAGE</td></tr><tr><td>0x4005</td><td>DMLERR_EXECACKTIMEOUT</td></tr><tr><td>0x4006</td><td>DMLERR_INVALIDPARAMETER</td></tr><tr><td>0x4007</td><td>DMLERR_LOW_MEMORY</td></tr><tr><td>0x4008</td><td>DMLERR_MEMORY_ERROR</td></tr><tr><td>0x4009</td><td>DMLERR_NOTPROCESSED</td></tr><tr><td>0x400a</td><td>DMLERR_NO_CONV_ESTABLISHED</td></tr><tr><td>0x400b</td><td>DMLERR_POKEACKTIMEOUT</td></tr><tr><td>0x400c</td><td>DMLERR_POSTMSG_FAILED</td></tr><tr><td>0x400d</td><td>DMLERR_REENTRANCY</td></tr><tr><td>0x400e</td><td>DMLERR_SERVER_DIED</td></tr><tr><td>0x400f</td><td>DMLERR_SYS_ERROR</td></tr><tr><td>0x4010</td><td>DMLERR_UNADVACKTIMEOUT</td></tr><tr><td>0x4011</td><td>DMLERR_UNFOUND_QUEUE_ID</td></tr></table>	Code	Description	0x4001	DMLERR_BUSY	0x4002	DMLERR_DATAACKTIMEOUT	0x4003	DMLERR_DLL_NOT_INITIALIZED	0x4004	DMLERR_DLL_USAGE	0x4005	DMLERR_EXECACKTIMEOUT	0x4006	DMLERR_INVALIDPARAMETER	0x4007	DMLERR_LOW_MEMORY	0x4008	DMLERR_MEMORY_ERROR	0x4009	DMLERR_NOTPROCESSED	0x400a	DMLERR_NO_CONV_ESTABLISHED	0x400b	DMLERR_POKEACKTIMEOUT	0x400c	DMLERR_POSTMSG_FAILED	0x400d	DMLERR_REENTRANCY	0x400e	DMLERR_SERVER_DIED	0x400f	DMLERR_SYS_ERROR	0x4010	DMLERR_UNADVACKTIMEOUT	0x4011	DMLERR_UNFOUND_QUEUE_ID
Code	Description																																				
0x4001	DMLERR_BUSY																																				
0x4002	DMLERR_DATAACKTIMEOUT																																				
0x4003	DMLERR_DLL_NOT_INITIALIZED																																				
0x4004	DMLERR_DLL_USAGE																																				
0x4005	DMLERR_EXECACKTIMEOUT																																				
0x4006	DMLERR_INVALIDPARAMETER																																				
0x4007	DMLERR_LOW_MEMORY																																				
0x4008	DMLERR_MEMORY_ERROR																																				
0x4009	DMLERR_NOTPROCESSED																																				
0x400a	DMLERR_NO_CONV_ESTABLISHED																																				
0x400b	DMLERR_POKEACKTIMEOUT																																				
0x400c	DMLERR_POSTMSG_FAILED																																				
0x400d	DMLERR_REENTRANCY																																				
0x400e	DMLERR_SERVER_DIED																																				
0x400f	DMLERR_SYS_ERROR																																				
0x4010	DMLERR_UNADVACKTIMEOUT																																				
0x4011	DMLERR_UNFOUND_QUEUE_ID																																				

See also

[DDEADVISE](#) event, [DDESERVICE](#) property, [DDETOPIC](#) property, [DDEITEM](#) property, [DDECOMMAND](#) property, [DDEDATA](#) property.