

# Printer Statement

## Description

Directs output of Print statement to the printer.

## Syntax

**Printer** On | Off | *numeric\_expression*

## Parameters

The Printer statement has the following parameters.

Parameter	Description
On	After a Printer On statement, all subsequent output from the Print statement is routed to the current printer device.
Off	A Printer Off statement closes the print job.
numeric_expression	You can also use a numeric expression. If numeric_expression evaluates to true (non-zero), Printer On is set. If the value of the expression is false (zero) or null, Printer Off is set.

## See also

[Print\\_Text](#)

## Example

```
/* The printer will print the current system date in the D2 format. */
Printer On
Print OConv(Date(), "D2")
Printer Off
```